



Set Alternate Count Units

Quick Start Guide

Document Details

Document #: 160_QS1000_220630

Release Version: 10.00.00.00

Version Release Date: July 2022

System Requirements

- CES Version 10.00.00 or higher



Be sure to grab the latest version of this document here:

<https://links.crunchtime.com/NCQS-SetAlternateCountUnits>

OR by scanning the QR code to the left.



Watch the tutorial on MainCourse:

<http://links.crunchtime.com/NCI102wkrr>

Other Related Documentation

- NCQS – Manage Storage Locations: <https://links.crunchtime.com/NCQS-ManageStorageLocations>

Related User Group Permissions

Screen Name	Control Name	Description
NC-Administrative Options	Inventory Setup	Enables this option on the Inventory menu.
NC-Administrative Options	Set Count Units	Enables the Inventory Unit link in the Inventory Setup screen to allow users to define/edit Alt Units.



Set Alternate Count Units

Alternate Count Units

In many cases, product may be stored in unique pack sizes in different areas throughout the store. Alternate Count Units allow users to enter inventory counts in a size other than the inventory unit, making it easier to accurately count how much product is in each storage.



Setup: Only users with the “NC-Administrative Options > Set Count Units” permission enabled will have the ability to add and edit alternate count units at the location level.

Net-Chef > Inventory: Inventory Setup

1 Select the desired *Storage Location* from the drop-down menu.

2 Select the *Inventory Unit* hyperlink.

3 Enter the *Conversion* factor and select the *Alt Units Package Type*. To determine the conversion factor ask yourself “How many Alt Units are in 1 Inventory Unit?”

4 Select the *Apply* button to add the new count units for this product. The alternate count unit will become available for all storage locations that have this product.

A Check/Uncheck the box in the *Display* column to show/hide this unit on the Count Sheet and Data Entry screens.

5 When you’re finished, select the *Disk* (Save) button.



Note: Alt Count Units can be setup at either the Corporate or Location level. Changes made to the alternate units in Net-Chef at the location level will not impact the alternate units for this company product in Enterprise Manager. Similarly, changes made to the alternate units in Enterprise Manager will not override alt units created at the local level.

